

Firmware Update Instructions using firmware not imbedded in FSData desktop

Installation Steps

1. Download instrument firmware from www.hach.com , save to location on computer.
2. Download, install and run FSData Desktop OR launch FSData Desktop if it is already installed.
3. Select “Connect”, top-right corner of FSData desktop.
4. On “Connect to Instrument” dialog.
 - a. Select desired instrument to update
 - b. Select port that is connecting to instrument
 - c. Select “Connect”
 - i. Top-right of client area will display “connected” if successful.
5. On main menu, located top-left by selecting arrow to right of FSData Desktop logo.
 - a. Select “Instrument Tools”
 - b. Select “Firmware Update”
6. Browse to correct firmware version downloaded from www.hach.com website.
 - a. select “Update”

Installation Verification

After the firmware update, navigate the instrument’s UI to verify the firmware versions. Main Menu | General Settings | About: